## NOAA Technical Memorandum ERL ARL-112

USER'S GUIDE FOR A LONG-RANGE MULTI-LAYER ATMOSPHERIC TRANSPORT AND DISPERSION MODEL

Roland R. Draxler

Air Resources Laboratories Silver Spring, Maryland May 1982



NATIONAL OCEANIC AND ATMOSPHERIC ADMINISTRATION

John V. Byrne, Administrator Environmental Research Laboratories

George H. Ludwig Director

# TABLE OF CONTENTS

	ABSTRACT	•		•	 •	•	•	•	•	•	•	•		íV
1.	TRANSPORT AND DISPERSION MODEL . 1.1 Model Structure 1.2 Advection Calculation Method	 •				•		٠					٠	]
2.	MODEL PARAMETERS			•	 •					•	•	•		1
3.	EXAMPLE OUTPUT	 •	• •	•			•	•	•	•	•			4
4.	AVAILABILITY			•	 •		•	•		•			•-	9
5.	ACKNOWLEDGEMENTS			•		•			•	•	•	•		5
6.	REFERENCES			•	 •		•	•		•	•	•		6
	APPENDIX	 •		•									•	11

## **ABSTRACT**

A long-range transport and dispersion model which is responsive to the effects of wind shear is documented in this report. The model is especially suitable for calculating concentrations for puff travel times of greater than one day. The effect of wind shear on dispersion is obtained by dividing the pollutant puff within the mixed layer into 300m sublayers at the begining of each night. Each layer is tracked by means of a separate trajectory. Vertical mixing is resumed during the next day. Further puff divisions occur each night. Example calculations using the model are presented. Descriptions of necessary input parameters are related to the example calculations. The computer code is listed in the Appendix.

# USER'S GUIDE FOR A LONG-RANGE MULTI-LAYER ATMOSPHERIC TRANSPORT AND DISPERSION MODEL

## Roland R. Draxler

National Oceanic and Atmospheric Administration Air Resources Laboratories 6010 Executive Blvd. Rockville, Maryland 20852

May 1982

## 1. TRANSPORT AND DISPERSION MODEL

A brief discussion of the model is presented in this report. The long-range transport and dispersion model was described in detail by Draxler (1982). In that paper, model calculations were compared with measured concentrations from the 1974 Midwest Experiment first reported by Ferber et al. (1977). From January to May twice-daily measurements of Kr-85 air concentrations were made at 11 sites along a north-south line about 1500km from the source. Model calculations at the more southern sampling sites compared very favorably with the measured data. Incorporating wind-shear effects in long-range transport calculations was shown to reduce concentration overcalculations from models (as tested by Ferber et al., 1977) that do not consider wind-shear.

The wind-shear effect on a pollutant puff results from the absence of vertical mixing at night. During this time each vertical layer decouples and continues as a separate trajectory. The greater the wind-shear the greater the displacement of these layers from each other. During the daytime vertical mixing resumes and these elevated layers mix to the surface to affect air concentrations. Draxler and Taylor (1982) have shown that this approach to wind-shear simulation using actual meteorological data gives average puff growths that are similar to the theoretical growth of a puff in an Ekman boundary layer.

#### 1.1 Model Structure

The model is essentially a simple Lagrangian puff trajectory model. Twice-daily rawinsonde observations are used to calculate trajectories from a single source at 3-h intervals. However, to efficiently compute the trajectories of many more puffs the position of each element (endpoints, receptors, rawinsondes, etc.) of the calculations is indexed to a three-dimensional grid with a one-degree horizontal resolution and 10 vertical coordinates spaced at 300m increments. In this way, advection and air concentration calculations can be performed quickly without having to search an entire data array for the nearby receptors and rawinsondes.

Trajectory calculations, although time consuming due to the daily exponential increase in the number of trajectories, are not unduly

expensive. Several other features of the computer code, in addition the indexing by grid position, were designed to increase computational efficiency. For example,

1 - Sines and cosines are pre-computed and stored by whole degrees (the resolution of the wind directions);

2 - no spatial or temporal interpolation of meteorological

data is performed;

3 - the masses of two or more puffs at the same grid coordinates are combined; and

4 - any individual puffs whose mass has become too small to resolve in the air concentrations are eliminated.

# 1.2 Advection Calculation Method

Wind shear effects are incorporated by applying the diurnal difference in vertical mixing to the winds in the layer used to calculate advection. If the release is at night, the puff constrained to the lowest transport layer (0 to 300m). During the day, all puffs are assumed to mix instantaneously to the top of the mixed layer. During the next night, when no vertical mixing is assumed, the mass of a puff is divided into 300m layers within the previous day's mixed layer. The interval of 300m was chosen for the maximum vertical resolution because the wind data are reported at approximately that interval.

After a puff is divided, the layers are followed as separate trajectories for all subsequent calculations. During the next day, the layers become fully mixed to the surface. If the mixed layer during subsequent day-time periods is lower than the previous day some puffs may remain above the new mixed layer. These puffs will be advected with the appropriate wind in that upper layer and will not affect surface air concentrations until the mixed layer reaches that height. Mixed layer heights are determined within the model from the observed temperature soundings.

The separation of these vertical layered puffs simulates the wind shear effect. However, turbulent diffusion still plays a role in spreading the pollutant puff during the first 24 hours before wind shear begins to dominate horizontal dispersion. Therefore, turbulent dispersion is modeled by assuming that each puff expands with time as defined by Heffter (1965). Concentrations are assumed to be uniform across this disk. The concentration in the disk is then just the mass (variable - QTERM) of the pollutant divided by the cross-sectional area of the disk times its depth. Concentration calculations are performed at the advection time step (3h) at all grid locations (every one-degree latitude and longitude intersection).

## 2. MODEL PARAMETERS

Most model calculations can be controlled through the input parameters rather than modifying the code. About 150k bytes of computer core are required if the maximum number of puffs is 5000. Computer time requirements also vary according to the number of puffs. Slower wind speeds during the summer months mean that the number of puffs that pass off the computational grid are less than those in winter. Puffs are retained in the calculations until they pass off the grid. On an IBM 360/195, cpu time varies from 1.5 to 3.0 min per month of simulation time.

Unit numbers 5 through 10 are necessary for input and output. Unit 5 is reserved for the input cards to control the simulation. Units 6 through 9 are reserved for printing model output. Input meteorological data are read from unit 10. Meteorological data are available from the National Climatic Center, Digital Products Section, Asheville, North Carolina 28801. Each NCC tape contains 6 months of rawinsonde data and is identified by the time period. The tapes are called NAMER-WINDTEMP and are archived under the identifying number TD-9743.

# 2.1 Input Control Cards

Only three input cards are necessary to control most model simulations. Additional cards are needed to specify each fixed point receptor. Under most circumstances few other changes are necessary once the code is set to run for a particular region. The three necessary cards contain the parameters:

```
Card #1 - (variable; columns; format; description)
   IBDA 06-09 xxxx - Begining day of computations (01-31)
   IBMO 11-14 xxxx - Begining month of computations (01-12)
   NDTR 16-19 xxxx - Number of days of computations
   NAVG 21-24 xxxx - Number of 3hr periods for concentrations
  MAPS 26-29 xxxx - Flag for short (1) or long (0) map output
                      (80 or 132 columns)
  MAPC 31-34 xxxx - Flag for concentration maps to be printed
                      at NAVG interval (yes -1; no - 0)
  MAPT 36-39 xxxx - Number of 3hr periods between puff maps
Card #2 - (variable; columns; format; description)
  OLAT 06-09 xx.x - Origin latitude (degrees and tenths)
  OLON 11-15 xxx.x - Origin longitude (degrees and tenths)
  QTERM 17-21 xxxx. - Emissions per 3hr puff (arbitrary units)
  NQTRM 23-27 xxxxx - Number of 3hr puffs emitted starting at IBDA
  ALATT 29-33 xxx.x - Top latitude of calcualtional grid
 ALATB 35-39 xxx.x - Bottom latitude of computational grid
 ALONL 41-45 xxx.x - Left longitude of grid
 ALONR 47-51 xxx.x - Right longtitude of grid
```

Card #3 - (variable; columns; format; description)
 NREC 06-09 xxxx - Number of fixed point receptor positions

Card #4 to 'NREC+3' - (variable; columns; format; description)
RLAT 06-09 xx.x - Receptor latitude
RLON 11-15 xxx.x - Receptor longitude

The internal computational grid has been defined to be 25 degrees latitude by 60 degrees longitude. Therefore, the top internal boundary is always 25 degrees greater than the bottom. The left longitude just controls the alignment of all the output maps which are scaled by the top and bottom latitudes. All four boundaries are used to determine when puffs have passed off the computational grid. The intersection of the bottom and right boundaries is the origin (1,1) position of the internal computational grid.

## 2.2 Program Code Changes

There are some program constants within the code that would usually be changed only when the program is set up for a particular pollutant the first time. These involve the concentration factors needed to derive the correct units. The numeric value of 'CNFACT' determines the units of the input source term. All concentrations are multiplied by 'CNFACT' before printing. This value is determined by the user so that the concentration output will be in whole integers from 1 to 999.

The variable 'PMIN' is the minimum puff mass in units determined by the user (in conjunction with 'CNFACT'). Puffs with less than this mass are eliminated from the calculations after each day.

## 3. EXAMPLE OUTPUT

The output on unit 6 from a 2 day simulation with concentration and puff maps at 3-hour intervals is illustrated in Fig. 1. The data from the input cards are printed and some of the meteorological data, read every 12-hours, are summarized. These values are read from the input data tape to confirm that the correct meteorological data are being used in the simulation. Printed twice a day are the number of stations reporting, the minimum, mean, and maximum mixing depths (meters) for all stations, and the number of puffs on the computational grid at that time.

A sequence of puff position maps for the example calculation of Fig. 1 is shown in Fig. 2. For the purposes of this illustration the maps have been combined on a single page in which time goes from left to right and down at 3 hour intervals starting at the end of day 1. The time of the map is in the upper left corner of each box. Maps can be printed at the advection interval (3hr) or at any 3hr interval chosen by the user. In this series, each map shown is approximately 500km wide.

The printed digit identifies the layer of the puff. During the day puffs within the mixed layer, ones that intercept the surface to give ground-level air concentrations, are identified by the digit 'l'; puffs with a number other than 'l' are above the mixed layer and do not contribute to surface air concentrations. Each increment above 'l' represents a height increment of 300m. The top layer (2700-3000m) is identified by the zero digit. Note that at the end of the first nocturnal advection step (3Z - 2nd box) the previous day's fully-mixed puffs ('l') are now separating at different levels.

The same sequence of maps for puff concentrations is shown in Fig. 3. Again the time of the map is given in the upper left. The averaging interval is the interval between maps. Concentrations are given by as many as three digits. The units have been adjusted by the variable 'CNFACT'. Concentrations greater than 999 are represented by '###'. The concentrations are printed at all whole degree latitude-longitude grid intersections. This is the current minumum resolution of the model concentration calculations. Fixed receptors are internally defined by the one-degree intersection point. The concentrations shown in Fig. 3 only correspond to puffs in Fig. 2 at the surface identified by 'l'. As in the previous example the additional puffs (index .1) at night (3Z) do not contribute to concentration at the surface until the next day (15Z map).

The table of receptor concentrations is shown in Fig. 4. The receptors numbered one to 'NREC' are those given in the input. The concentrations at these points are printed at the interval specified, in this case every three hours. These numbers also correspond with the concentrations shown in Fig. 3 at the appropriate grid intersection. The concentrations at these fixed receptors is taken internally from the computational grid.

## 4. AVAILABILITY

A copy of the computer code (FORTRAN) is listed in the Appendix. Magnetic tape copies may be obtained from the author.

## 5. ACKNOWLEDGEMENTS

This work was supported by the U.S. Department of Energy, Office of Health and Environmental Research.

## 6. REFERENCES

- Draxler R.R. (1982) Measuring and modeling the transport and dispersion of Krypton-85 1500km from a point source, to be published in <a href="https://example.com/Atm.Environm">Atm. Environm</a>.
- Draxler R.R. and Taylor A.D. (1982) Horizontal dispersion parameters for long-range transport modeling, <u>J. Appl. Meteorol</u>., March.
- Ferber G.J. Telegadas K. Heffter J.L. and Smith M.E. (1977) Air concentrations of Krypton-85 in the midwestern United States during January-May 1974, <a href="https://example.com/Atm.environm...">Atm. Environm...</a>, 11:379-385.
- Heffter J.L. (1965) The variation of horizontal diffusion parameters with time for travel periods of one hour or longer, <u>J. Appl. Meteorol.</u>, <u>4</u>:153-156.

## INPUT PARAMETERS

IBDA IBMO NDTR NAVG MAPS MAPC MAPT

1 1 2 1 0 1 1

OLAT OLON QTERM NOTRM ALATT ALATB ALONL ALONR

40.0 100.0 3000. 16 50.0 25.0 110.0 65.0

NUMBER OF FIXED POINT RECEPTORS

NREC

1

RLAT RLON

43.0 95.0

FIN.	ISHED RE	RADING	MET	EORO:	LOGICAL	DATA	MIXING	DEP	TH DA	ATA (m	eters)	
	MONTH	YEAR	DAY	-HR		REPOR	rs Mi	IN M	IEAN	MAX	PUFFS	
	JAN	1975	1	12		55	53	30 1	620.	4456	0	
	JAN	1975	2	0		62	49	91 1	736.	4943	4	
	JAN	1975	2	12		72	4	17 1	426.	4799	34	
	JAN	1975	3	0		64	58	BO 1	586.	5147	38	
1												

Figure 1. Illustration of output from unit 6 for sample calculation.

Data from input cards are printed and certain meteorological data each time period are sumarized as read from the input tape.

DAY 1 TIME 24Z	DAY 2 TIME 3Z	DAY 2 TIME 6Z
•		
		_
		3 3 2 3
	3 23	3 2 2 3 4 5 6 1 3 6 7
	23 2 <sup>23</sup> 6 7 2 34 5 32 6 1 2 7 1 2 6	2,1 3 9
1	2 345 32 6	3 7 1 1 65 4
1 1 1	1 2 7	1
s 1	1 2 6 8 8 2 1	s 1 2
1		
DAY 2 TIME 9Z	DAY 2 TIME12Z	DAY 2 TIME 15Z
	3	1 1
	2 2 3	1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1
3 2	3 <sup>2</sup> 3 2 35443 4 6 c	1, 18
3 2 4 3	2 265 <sub>3</sub> 7	1 1
<sup>2</sup> <sup>4</sup> 36 56 7	7	1 1 1
2 3 2 4 3 2 4 563 4 36 56 7 1 2 5 7 1 3 6 6 4	1 1 2 4 6	1 1
1 <sup>1</sup> 1 6 <sub>5</sub> 4 1 2 3	1	
. 1	1	1 1
1 1 2	1 1	1 1 1
s 1	s 1	1 S <sub>1</sub> 1
		DAY2 TIME 24Z
DAY 2 TIME 18Z	11	
1 1	111	
11, 1	1 1	1 1
11 1	1 1	1
1 1	1	1
1 1	1 1	1 1
1 1	1	1 1
1	1 1	1
1	1	1
i .	s	s , ,
1 5 1	11.4	1 1 1 1

Figure 2. Illustration of output from unit 8 for sample calculation. Shown are the positions of the puffs at three hour intervals. Puffs in the surface layer are identified by the digit 'l'. Elevated puffs have digits from 2 to 0. The height is the value of the digit times 300m. The position of the source is indicated by 'S'.

DAY 1 TIME 24Z	DAY 2 TIME 3Z	DAY 2'TIME 6Z
l		
		. !
	423	423 294
661	***	### 108
***** 212	### 147	### 142
### 240 S 71	### 185 S 56	S 45
	30	45
DAY 2 TIME 9Z	DAY 2 TIME 12Z	DAY 2 TIME 15Z
		33
		22 41 52 54
		28 44 52
		20 15 13
		7 12 5
216	381	33 9 12 3
717 83	254 294 65	24 4
***	***	127 18 12 13
### 112	*** *** 91 31	ļ
\$ 37	s	198 13 S 353 *** 9
	31	333 1 1 3
DAY 2 TIME 18Z	DAY 2 TIME 212	DAY 2 TIME 24Z
57 31 76	9 54	16
27 60 43	27 54	<sub>1</sub> 20 16
6 20 47 2	10 19 13	· ·
14 6 5 16 2	19	
682	4 2	8 3
15 12 5 4	21 4 3	36 6 11 3
18 4 4		8 12 17 9
10 12	15 4 9 3	9 17 9
10 12	12 3 3	212 6 6 6
588 10 8	331 3 3 3	
\$ 10†159 <i>****</i>	S ******	S ***** 661
101 129	*****	<u> </u>

Figure 3. Illustration of the output from unit 9 for the sample calculation. Shown are the 3-hour average concentrations. Only puffs in the surface layer (digit - 1 in Fig. 2) contribute to air concentrations.

END SAI	MPLING	RECEPTORS	
DAY	HR	1,	
1	3	0.0	
1	6	0.0	
1	9	0.0	
1	12	0.0	
1	15	0.0	
1	18	0.0	
1	21	0.0	
1	24	0.0	
2	3	0.0	
2	6	0.0	
2	9	0.0	
2	12	0.0	
2	15	0.0	
2	18	3.9	
2	21	8.9	
2	24	12.3	_

Figure 4. Illustration of output from unit 7 for the sample calculation. Shown are the 3-hour concentrations (arbitrary units) at a fixed receptor identified in the input cards shown in Fig. 1.

#### APPENDIX

## Listing of Code

```
DATA IMAPS/0/
-----CONCENTRATION FACTOR TO GIVE INTEGER UNITS ON OUTPUT
CNFACT=1.0E+12
 00001000
00001100C
00001200
                                                         ----MINIMUM PUFF MASS (ARBITRARY UNITS)
                                                           PMIN=1.0
  00001300C-
                                                                                                    M CONTROL INPUT PARAMETERS
BEGINING DAY OF COMPUTATIONS
BEGINING MONTH OF COMPUTATIONS
NUMBER OF DAYS OF COMPUTATIONS
NUMBER OF 3HR CONCENTRATION AVERAGES
FLAG FOR SHORT OR LONG MAP OUTPUT (80 OI
0 - 132 COLUMN PRINTER; 1 - 80 COLUMN PI
CONCENTRATION MAP FLAG (0/1) AT NAVG INT
NUMBER OF 3HR PERIODS BETWEEN PUFF MAPS
ORIGIN LATITUDE (DEG-TENTHS)
ORIGIN LONGITUDE (DEG-TENTHS)
EMISSIONS PER 3 HOUR PUFF
NUMBER OF 3 HOUR PUFF
NUMBER OF 3 HOUR PUFF
TOP LATITUDE OF GRID (DEG-TENTHS)
                                                       ----PROGRAM CONTROL INPUT PARAMETERS
 00001400C
00001500C
00001600C
00001700C
                                                                           IBDA
                                                                           IBMO
                                                                           NDTR
                                                                           NAVG
  0000<u>1800</u>Č
                                                                                                                                                                                                                                                    (80 OR 132)
                                                                          MAPS
 00001800C
00001900C
00002100C
00002200C
00002300C
00002400C
00002500C
                                                                                                                                                                                                                 - 80 COLUMN PRINTER
/1) AT NAVG INTERVAL
                                                                          MAPC
MAPT
                                                                           OLAT
                                                                          OLON
                                                                           QTERM-
                                                                           NOTRM-
                                                                           ALATT-
                                                                                                        TOP LATITUDE OF GRID (DEG-TENTHS)
  00002700C
00002800C
00002900C
00003000C
                                                                                                       BOTTOM LATITUDE
                                                                           ALATB-
                                                                           ALONL- LEFT LONGITUDE
                                                                       ALONE- RIGHT LONGITUDE ...
-INPUT/OUTPUT FILE REQUIREMENTS
-T05F001 - PROGRAM CONTROL INPUT PARAMETERS
 00003100C
00003100C
00003200C
00003300C
00003500C
00003600C
                                                                           FT05F001 -
FT06F001 -
FT07F001 -
                                                                                                                        PRINTER OUTPUT FOR RUN STATISTICS
                                                                                                                        PRINTER OUTPUT FOR FIXED SAMPLING SIT PRINTER OUTPUT FOR PUFF POSITION MAPS PRINTER OUTPUT FOR CONCENTRATION MAPS
                                                                                                                        PRINTER
                                                                                                                                                                                                                                                                  SITES
                                                                           FT08F001
                                                                            PT09F001
                                                                                                                        INPUT METEOROLOGICAL DATA
                                                                           FT10F001
                                                                                                                        NAMER-WINDTEMP TAPES
                                                                                                                                                                                                               (TD-9743)
                                                                                                                                                        DIGITAL PRODUCTS
  000038000
                                                                                                                        ASHVILLE, NC
  000039000
                                             ASHVILLE, NC 28801

WRITE(6,20)

PORMAT(1X, 'INPUT PARAMETERS')

WRITE(6,25)

FORMAT(6X, 'IBDA IBMO NDTR NAVG MAPS MAPC MAPT')

READ(5,50) IBDA, IBMO, NDTR, NAVG, MAPS, MAPC, MAPT

FORMAT(5X,7(14,1X))

WRITE(6,60) IBDA, IBMO, NDTR, NAVG, MAPS, MAPC, MAPT

WRITE(6,75)

FORMAT(6X,7(14,1X))

WRITE(6,75)

FORMAT(6X, 'OLAT OLON QTERM NQTRM ALATT ALATB ALONL',

* ALONR')

READ(5,100) OLAT, OLON, OTERM, NOTRM, ALATT, ALATB, ALONL, ALONG, A
 00004000
00004100
00004200
00004300
  00004400
  00004500
  00004600
  00004700
  00004900
                                           READ(5,100)OLAT,OLON,OTERM,NOTRM,ALATT,ALATB,ALONL,ALONR
100 FORMAT(5X,F4.1,1X,F5.1,1X,F5.0,1X,15,4F6.1)
WRITE(6,120)OLAT,OLON,OTERM,NOTRM,ALATT,ALATB,ALONL,
* ALONR
  00004910
 00005000
00005100
00005200
00005210
00005300
00005400
                                          * ALONR
120 FORMAT (6X,F4.1,1X,F5.1,1X,F5.0,1X,15,4F6.1)
    WRITE (6,110)
110 FORMAT ('NUMBER OF FIXED POINT RECEPTORS',/
    READ (5,125) NREC
125 FORMAT (5X,14)
    WRITE (6,126) NREC
126 FORMAT (6X,14)
    IF (NREC.EO.0) GO TO 149
    WRITE (6,128)
128 FORMAT ('RLAT RLON')
  00005500
00005600
00005700
                                                                                               NUMBER OF FIXED POINT RECEPTORS', /, 6X, 'NREC')
  00005800
00005900
  00006000
  00006100
00006200
```

```
DO 140 I=1,NREC
READ(5,130)RLAT(I),RLON(I)
FORMAT(5X,F4.1,1X,F5.1)
WRITE(6,135)RLAT(I),RLON(I)
FORMAT(6X,F4.1,1X,F5.1)
00006300
00006400
 00006500
00006600
00006700
00006800
00006900
00007000
00007100
00007200
                                    CONTINUE
WRITE (7,144) (I,I=1,NREC)
FORMAT ( END SAMPLING )
WRITE (7,146)
                          140
                                                                                               RECEPTORS',/,' DAY HR',5X,1015)
                          144
                                                      146)
                          146
                                    FORMAT
                                    CALL CNZERÓ
                          149
                                               MPLOT (MAPS)
INITLZ (NPUFF)
PSTNTP (IBMO, IBDA)
00007400
00007500
00007600
                                     CALL
                         CALL PSTNTP(1BMU,1BL,,
CALL SKIP(2)
WRITE(6,150)

150 FORMAT(1H0, FINISHED READING METEOROLOGOCAL DATA',14X,

* 'MIXING DEPTH DATA (M)',/,6X,'MONTH',2X,'YEAR',1X,

* 'DAY-HR',18X,'REPORTS',4X,

* 'MIN',1X,'MEAN',3X,'MAX',5X,'PUFFS')
IF(NAVG.EQ.1)CALL CNZERO
DO 1000 I=1,NDTR
DO 900 ITIME=3,24,3
IF(IMAPS.GE.MAPT)IMAPS=0
00007700
 00007800
00007900
 00008000
00008100
00008200
00008300
                                                              DO 900 ITIME=3,24,3
IF (IMAPS.GE.MAPT) IMAPS=0
IMAPS=IMAPS+1
00008500
 00008600
 00008700
                                                               IF(IFIX(TS).GE.NAVG)CALL CNZERO
TS=TS+1.0
 00008800
 00008900
                                                              TS=TS+1.0

IGMT=ITIME-3

CALL RDMTDT(NPUFF, IGMT, &800)

CALL ASSIGM(IDSTN)

CALL ADVCTN(NPUFF, IGMT, OLAT, OLON, OTERM, NOTRM)

IF(IMAPS.GE.MAPT)CALL PFPLOT(I, ITIME, NPUFF,
 00009000
00009100
 00009200
00009300
00009400
00009410
                          800
                                                              IF (IMAPS.GE.MAPT) CALL PFPLOT (I, ITIME, NPUFF, OLAT, OLON)
IF (MAPC.EQ.1.AND.IFIX(TS).GE.NAVG) CALL CNPLOT (I, ITIME, OLAT, OLON)
IF (IFIX(TS).GE.NAVG) CALL CNPRNT (I, ITIME)
00009500
ŎŎŎŎŌŢQQ
 00009800
                          900
                                                               CONTINUE
00009900
00010000
00010100
00010200
                                                 CALL PCNVRG(NPUFF)
CALL PSORT(NPUFF, PMIN)
CALL PSPLIT(NPUFF)
                       1000
                                                 CONTINUE
00011500
00011500
00011600
00011700
00011900
00012100
000122100
00012300
00012300
00012500
00012600
00012600
00012700
00012900
00013900
00013900
                             10 NSTA=0
                                     NTEMP=0
                                     AVGMX=0
                                    MINMX=3000
                                    MAXMX=0
                                                INITL2
DO 300 I=1,2
READ(10,30,END=400,ERR=412)MON,IYR,IDY,IHR,NREPT
FORMAT(A3,14,12,12,14)
IF(NREPT.EO.0)GO TO 300
DO 200 J=1,NREPT
READ(10,40,END=400,ERR=412)LATSTA,LONSTA,
IHTSTA,NLVLS
FORMAT(5X,I5,17,15,5X,12)
IF(NLVLS.EO.0)GO TO 200
DO 100 K=1,NLVLS
GO TO(50,75),I
READ(10,45,END=400,ERR=400)IHT,IWDR,IWSP
FORMAT(15,13,14)
                                    CALL
                                                 INITL2
                             30
                             40
 00013200
00013300
                                                                            FORMAT (15,13,14)
IF (K.GT.20) GO TO 100
                                                                            IZHT(K)=MAXO(IHT-IHTSTA,0)
 00013400
```

```
00013500
00013600
00013700
00013800
00013900
00014000
00014100
                                                                           ISPD(K) = IWSP/10.0+0.5
IDIR(K) = IWDR
IF(IDIR(K).EQ.0)IDIR(K) = 360
GO TO 100
                                                               GO TO 100
READ(10,47,END=400,ERR=400)IHT,IPRES,IDEG
FORMAT(14,15,14)
IF (K.GT.20)GO TO 100
IZHT(K)=MAXO(IHT-IHTSTA,0)
IPPP(K)=IPRES/10.0+0.5
ITEMP(K)=IDEG
CONTINUE
IF (NLVLS.GT.20)NLVLS=20
IF (NLVLS.LE.1)GO TO 200
STALAT=LATSTA/100.0
                               75
     00014200
00014300
00014400
    00014500
00014600
00014700
00014800
                             100
                                                               IF (NLVLS.LE.1) GO TO 200
STALAT=LATSTA/100.0
STALON=LONSTA/100.0
CALL INDEX1(STALAT,STALON,ILAT,JLON,IREM,&200)
GO TO(110,120),I
CALL WBANW(NSTA,ILAT,JLON)
CALL WDTMP(NLVLS,NSTA)
GO TO 200
CALL WBANT(NSTA,ILAT,JLON, 1200)
     00014900
00015000
    00015000
00015100
00015200
00015300
00015500
00015600
00015700
00016000
00016100
00016300
00016300
00016500
                             110
                                                               CALL WBANT (NSTA, ILAT, JLON, 6200)
CALL TMPRFL (NLVLS, NSTA, MIX)
NTEMP=NTEMP+1
                             120
                                                               AVGMX=AVGMX+MIX
                                                               MINMX=MINO(MINMX,MIX)
MAXMX=MAXO(MAXMX,MIX)
                              200
300
                                                                 CONTINUE
                                                   CONTINUE
                                       CALL WBANF
AVGMX=AVGMX/NTEMP
     00016500
00016510
00016600
00016610
00016700
00016900
00017100
                                       WRITE (6,550) MON, IYR, IDY, IHR, NTEMP, MINMX, AVGMX, MAXMX,
                             550 FORMAT (6X,A3,3X,I4,2(2X,I2),18X,I5,5X,I4,1X,F5.0,1X,I4,
                                      GO TO 420
WRITE (6,410)
FORMAT (1H0, EOF ON UNIT 10 FROM RDMTDT')
                              400
                              410
                                        STOP
     WRITE(6,414)
FORMAT(1H0, 1/O ERROR ON UNIT 10 FROM RDMTDT')
                                       IF(IBDA.EQ.1.OR.IBDA.EQ.16)RETURN
ISKIP=(IBDA-1)*4
IF(IBDA.GE.16)ISKIP=(IBDA-16)*4
ENTRY SKIP(ISKIP)
DO 100 I=1,ISKIP
DO 100 J=1,2
READ(10,20,END=110,ERR=130)NREC
FORMAT(15X,I5)
IF(NREC.EQ.0)GO TO 100
DO 90 K=1,NREC
READ(10,30,END=110,ERR=130)
FORMAT(')
FORMAT(')
CONTINUE
CONTINUE
RETURN
```

```
00020700C
00020800
000220900
00021100
00021100
00021300
00021500
00021500
00021500
00021600
00022100
00022100
000222000
000222300
000222300
000222300
000222600
000222700
000222800
                                                                                                                                                             EACH VARIABLE IN MSTNS COMMON BLOCK
                                                                                                                                SUBROUTINE WBANX
INTEGER*2 IDSTN(25,60)
COMMON/MSTNS/IDSTN, DUMMY(1800)
ENTRY WBANW(NSTA, ILAT, JLON)
                                                                                                                                 NSTA=NSTA+1
                                                                                                                                IDSTN(ILAT, JLON) = NSTA
RETURN
                                                                                                                                 ENTRY WBANT (NSTA, ILAT, JLON, *)
IF (IDSTN (ILAT, JLON) . EQ. 0) RETURN 1
NSTA=IDSTN (ILAT, JLON)
IDSTN (ILAT, JLON) = - IDSTN (ILAT, JLON)
                                                                                                                                  RETURN
                                                                                                                                 ENTRY WBANF
                                                                                                                                                                              DO 100 I=1,25

DO 100 J=1,60

IF(IDSTN(I,J).LE.0)GO TO 100

IDSTN(I,J)=0

CONTINUE
| CONTINUE | COMMON BLOCK MSTNS | COMMON PART | CONTINUE | CONTINUE | CONTINUE | COMMON BLOCK MSTNS | COMMON PART | COMMON BLOCK MSTNS 
                                                                                               100
                                                                                                                                  RETURN
         00027600
00027700
                                                                                                  MIX=2999
GO TO 210
200 MIX=IZHT(I)
          00027800
          00027900
```

```
00028000
00028100
                                                         210 MIXH(NSTA)=MINO(MIX,2999)
                                                                              RETURN
00028200 END
00028300C-----
00028400C******
00028500C
00028600C
00028800 SUB
00028900 INT
00028910 *ID
00029100 COM
00029200 COM
00029300 MIX
00029400 MIX
00029400 LB=
00029700 LB=
00029700 LT=
  00028200
                                                                              END
                                                                                               SUB TO COMPUTE HORIZONTAL AVERAGED WIND FOR ADVECTION NOTE THAT AFTER STMT 60 THE SECTION IS SET TO SCAN SOUNDING IF THERE ARE MISSING DATA AT A LEVEL
                                                                              OTHERWISE NO ADVECTION IS CALCULATED ON THE 3RD PASS SUBROUTINE WINDWT (NWIND, LBT, LTT, XTS, YTS, *) INTEGER*2 WDIR (100,10), WSPD (100,10), MIXH (100),
                                                                             INTEGER 2 WOIR (100,10), WSPD (100,10), MIXII (100,10), MIXIII (100,10), MIXIIII (100,10), MIXIII (100,10), MIXIII (100,10), MIXIII (100,10), MIXIII (100,10), MIXIIII (100,10), MIXIIII (100,10), MIXIIII (100,10), MIXIII (100,10), MIXIII (100,10), MIXIII (100,10), MIXII
                                                                               IC=0
 00029700
00029700
00029900
00029900
00030100
00030200
00030400
00030500
00030500
00030500
00031100
00031200
00031300
                                                                               LB=LBT
                                                                                 LT=LTT
                                                                              XAW=0.0
                                                                               YAW=0.0
                                                                               INW=0
                                                                                                          DO 50 K=LB,LT

ISPD=WSPD(NWIND,K)

IDIR=WDIR(NWIND,K)

IF(IDIR.LT.0.OR.ISPD.LT.0)GO TO 50

XAW=XAW-ISPD*SIN360(IDIR)

YAW=YAW-ISPD*COS360(IDIR)
                                                                              CONTINUE
IF (INW. NE. 0) GO TO 100
IC=IC+1
                                                               50
                                                                              GO TO (60,70,200), IC
IF (LB.GT.MIX) GO TO 65
REAL*4 MASS (05000), COS360 (360), SIN360 (360), COSLAT (25)
COMMON/PUFFS/MASS, POSTN, ARRAY, SIGMA
COMMON/TRANS/COS360, SIN360, COSLAT
COMMON/MSTNS/IDSTN, WDIR, WSPD, MIXH, DUMMY (750)
DATA IOCNT/0/
   00034200
00034300
                                                                                IOCNT=IOCNT+1
IF(IQCNT.GT.NQTRM)GO TO 200
  00034400
00034500
00034600
00034700
                                                                                NPUFF=NPUFF+
                                                                               MASS (NPUFF) = OTERM
POSTN (NPUFF) = JREM
ARRAY (NPUFF) = ILAT*1000+JLON*10+1
                                                                                 SIGMA (NPUFF) = 0
                                                          200 IF (NPUFF.EQ.0) GO TO 600
   00034900
                                                                                                           DO 500 L=1,NPUFF
IF(MASS(L).EQ.0.0)GO TO 500
   00035000
00035100
```

```
IT1=ARRAY(L)/1000

JT1=ARRAY(L)/10-IT1*100

KT1=ARRAY(L)-ARRAY(L)/10*10

NW1=IDSTN(IT1,JT1)
00035200
00035400
000355000
000355700
000355700
000355900
000366100
000366200
000366400
000366700
000366700
000377200
000377400
                                                           NWI=IABS (NWI)
                                                           IF (NW1.EQ.0)GO TO 375
SIGMA(L)=SIGMA(L)+5
CALL LEVEL(NW1,KT1,IGMT,LB,LT)
CALL WINDWT(NW1,LB,LT,XTS,YTS,&325)
                                300
                                                           CALL WINDWT (NWI, LB, LT, XTS, YTS, &325)
IREM=POSTN(L)
CALL INDEX2(IREM, IT1, JT1, TLAT1, TLON1)
TLAT2=TLAT1+YTS/60.0
TLON2=TLON1-(XTS/(60.0*COSLAT(IT1)))
CALL INDEX1(TLAT2, TLON2, IT2, JT2, IREM, &375)
POSTN(L)=IREM
ARRAY(L)=IT2*1000+JT2*10+KT1
IT1=IT2
IT3-IT2
                                                           JTĪ=JT2
                                                           TSIGMA=SIGMA(L)*1000.0
IF(LB.EQ.1)CALL CNSUM(IGMT,LT,MASS(L),IT1,JT1,TSIGMA)
GO TO 500
MASS(L)=0.0
CONTINUE
                                325
                                375
500
AND ABOVE MIXED LAYER
                                            AND THE AVERAGE WITHIN THE MIXED LAYER DURING THE DAY SUBROUTINE LEVEL (NW1, KT1, IGMT, LB, LT) INTEGER 2 WDIR (100, 10), WSPD (100, 10), MIXH (100),
 00040100C**********SUB TO ARRANGE FOR PLOTTING DAILY PUFF POSITIONS
00040200C PUFFS THAT CONTRIBUTE TO SURFACE CONCENTRATION
00040300C ARE INDICATED BY INDEX 1, OTHERS HAVE LEVEL NUMB
00040400C THAT ARE MULTIPLES OF 300 METERS
00040500 SUBROUTINE PFPLOT(IDAY, ITIME, NPUFF, OLAT, OLON)
00040600 INTEGER*2 POSTN(05000), ARRAY(05000), SIGMA(05000)
00040700 LOGICAL*1 G, IJOFF, NUM(10)
                                                                                                                                                          HAVE LEVEL NUMBERS
                                           00040700
00040900
00041000
00041100
00041300
00041300
00041500
00041700
00041700
00041900
0004200
0004200
00042300
00042400
                                            DATA NUM/11, 12, 13, 14, 15, 16, 17, 18, 19, '0'/
T(ALAT) = ALOG(TALATT/TAN(0.785+ALAT*0.00873))
IJOFF(I,J) = I.LT.1.OR.I.GT.130.OR.J.LT.1.OR.J.GT.80
CALL PLTZRO
                                             IF (NPUFF.EQ.0) GO TO 600
DO 500 L=1, NPUFF
                                                           IF (MASS(L).EQ.0.0)GO TO 500
IREM=POSTN(L)
ITRAJ=ARRAY(L)/1000
JTRAJ=ARRAY(L)/10-ITRAJ*100
KTRAJ=ARRAY(L)-ARRAY(L)/10*10
IF (KTRAJ.EQ.0)KTRAJ=10
```

```
VARIABLE TS IS THE SAMPLING COUNTER, INCREMENTED EACH ADVECTION STEP. THE CONCENTRATION FACTOR OF E+12 IS APPLIED BEFORE PLOTTING TO GET WHOLE NUMBERS
                                                     SUBROUTINE CNCON
REAL*4 CONC(25,60), COSLAT(25), SIN360(360), COS360(360)
DIMENSION FXCON(10)
LOGICAL*1 G, IJOFF, NUM(10), AST, BLANK, OVRPRT
COMMON/MAPVAL/XGPD, YGPD, TALATT
COMMON/GRID/ALONL, ALONR, ALATT, ALATB
COMMON/TRANS/COS360, SIN360, COSLAT
COMMON/MAPGRD/G(130,80)
COMMON/CON/TS, CNFACT
COMMON/CON/TS, CNFACT
COMMON/RCPFX/RLAT(10), RLON(10), NREC
DATA YD/111180.0/
DATA NUM/'1','2','3','4','5','6','7','8','9','0'/
DATA AST/'*'/, BLANK/''/
T(ALAT) = ALOG(TALATT/TAN(0.785+ALAT*0.00873))
OVRPRT(I,J) = G(I-1,J).NE.BLANK.OR.

*
IJOFF(I,J)=I.LT.1.OR.I.GT.130.OR.J.LT.1.OR.J.GT.80
ENTRY_CNZERO
 00044800
000445000
00045100
00045200
00045300
00045300
00045500
00045500
00046500
00046200
00046300
00046500
                                                       IJOFF(I,J)=I.LT.1.
ENTRY CNZERO
DO 100 I=1,25
DO 100 J=1,60
CONC(I,J)=0.0
                                        100
                                                       TS=0
                                                       ŘĔTŮŘŇ
                                                       ENTRY CNSUM (IGMT, LT, TMASS, ITRAJ, JTRAJ, TSIGMA)
  00046500
00046600
00046700
                                                      ZD=300.0
IF(IGMT.GE.12)ZD=300*LT
ISCAN=(2.0*TSIGMA)/YD
JSCAN=(2.0*TSIGMA)/(YD/COSLAT(ITRAJ))
IMIN=MAX0(ITRAJ-ISCAN,1)
IMAX=MINO(ITRAJ+ISCAN,25)
JMIN=MAX0(JTRAJ-JSCAN,1)
JMAX=MINO(JTRAJ+JSCAN,60)
DO 150 I=IMIN,IMAX
DO 150 J=JMIN,JMAX
CONC(I,J)=CONC(I,J)+TMASS/(12.6*ZD*TSIGMA*TSIGMA)
CONTINUE
RETURN
   00046800
   00046900
00047000
   00047100
00047200
  00047200
00047300
00047400
00047500
00047600
                                        150
                                                       RETURN
                                                       ENTRY CNPLOT (1DAY, 1TIME, OLAT, OLON)
CALL PLTZRO
   00047800
  00047900
00048000
00048100
00048200
00048400
                                                        IF (TS.EO.0.0) GO TO 500
DO 400 IL=1,25
                                                                         DO 400 IL=1,25
DO 400 JL=1,60
SLAT=IL+(ALATB-1.0)+0.5
SLON=JL+(ALONR-1.0)+0.5
I=(ALONL-SLON)*XGPD+0.5
J=T(SLAT)*YGPD+0.5
IF(IJOFF(I-1,J))GO TO 400
IF(IJOFF(I+1,J))GO TO 400
IF(OVRPRT(I,J))GO TO 400
ICONC=CONC(IL,JL)/TS*CNFACT+0.5
IF(ICONC.LE.0)GO TO 400
IF(ICONC.LT.1000)GO TO 325
G(I-1,J)=AST
G(I,J)=AST
G(I+1,J)=AST
GO TO 400
   00048500
00048600
00048700
   00048700
00048900
00049000
00049100
00049200
   00049300
00049400
00049500
   ŎŎŎ49600
                                                                                      TÕ
                                                                                               400
   00049700
                                                                                              DO 350 IP=1,3
IV=ICONC-ICONC/10*10
                                         325
   00049800
```

```
****SUB TO PLOT DATA ON STANDARD PLANE PROJECTION
SUBROUTINE MPLOT (MAPS)
REAL*4 XLON(120), YLAT(76)
INTEGER*2 NI(2), NJ(2), LPI(2)
LOGICAL*1 G, BLANK, PLUS, SOURCE
COMMON/MAPVAL/XGPD, YGPD, TALATT
COMMON/GRID/ALONL, ALONR, ALATT, ALATB
COMMON/MAPGRD/G(130,80)
DATA BLANK/ '/, PLUS/'+'/, SOURCE/'S'/
DATA NI/120,70/, NJ/76,40/, LPI/8,6/
T(ALAT) = ALOG(TALATT/TAN(0.7853982+ALAT*0.008726646))
TALATT=TAN(0.7853982+ALATT*0.008726646)
TALATT=TAN(0.7853982+ALATT*0.008726646)
NIX=NI(MAPS+1)
NJY=NJ(MAPS+1)
XDPI=(-57.29578*LPI(MAPS+1)/NJY)*ALOG(TALATB/TALATT)
XGPD=10.0/XDPI
YGPD=LPI(MAPS+1)/(XDPI*0.01745329)
XLON(1)=ALONL
DO 100 LX=2,NIX
XLON(LX)=XLON(LX-1)-XDPI/10.0
CONTINUE
DO 200 J=1,NJY
YLAT(1)=114 5016*/ATAN/EVD/-1/YCDO)*TALATTNACO
                                                                                            DO 200 J=1,NJY
YLAT(J)=114.5916*(ATAN(EXP(-J/YGPD)*TALATT))-90.0
CONTINUE
      00057100
00057200
                                                                                              KE=J+\bar{3}
```

```
COMMON/MSTNS/IDSTN,WDIR,WSPD,MIXH,DUMMY(750)

COMMON/MSTNS/IDSTN,WDIR,WSPD,MIXH,DUMMY(750)

COMMON/MSTNS/IDSTN,WDIR,WSPD,MIXH,DUMMY(750)

RETURN

COSAGO (1) = COS (ANG)

COSA
                                                                                                                                                                             SIGMA (05000)
COMMON/PUFFS/MASS, POSTN, ARRAY, SIGMA
COMMON/PUFFS/MASS, POSTN, ARRAY, SIGMA
COMMON/MSTNS/IDSTN, WDIR, WSPD, MIXH, DUMMY (750)
IF (NPUFF, LT. 1) RETURN
L2=NPUFF+1
             00064100
00064200
00064300
00064400
```

```
00064500
                                              00064600
                                                                INTEGER*2 WDIR(100,10), WSDIR(103000), ARRAI(103000)
INTEGER*2 KDSTN(25,60), SIGMA(05000)
REAL*4 MASS(05000)
COMMON/PUFFS/MASS, POSTN, ARRAY, SIGMA
COMMON/PUFFS/MASS, POSTN, ARRAY, SIGMA
COMMON/MSTNS/IDSTN, WDIR, WSPD, MIXH, KDSTN
IF (NPUFF.LT.2) RETURN
DO 900 LOOP=1,2
DO 50 I=1,25
DO 50 J=1,60
KDSTN(I,J)=0
CONTINUE
DO 500 L=1,NPUFF
IF (MASS(L).E0.0.0)GO TO 500
IN=ARRAY(L)/10-IN*100
KN=ARRAY(L)/10-IN*100
KN=ARRAY(L)/10-IN*100
IF (KN.EQ.0) KN=10
IF (KN.EQ.0) KN=10
IF (KDSTN(IN,JN)) 100,100,200
KDSTN(IN,JN)=L
GO TO 500
LO=KDSTN(IN,JN)
KO=ARRAY(LO)-ARRAY(LO)/10*10
IF (KO.EQ.0) KO=10
GO TO (210,220), LOOP
IF (KO.EQ.0) KO=10
GO TO 500
KMET=IDSTN(IN,JN)
KMET=IABS(KMET)
KMIX=MINO(KMIX,10)
IF (KO.GT.KMIX) GO+1
KMIX=MINO(KMIX,10)
IF (MASS(LO).GT.MASS(L)) GO TO 500
ARRAY(LO)=IN*100+JN*10+1
IF (MASS(LO).GT.MASS(L)) GO TO 300
POSTN(LO)=POSTN(L)
    00069900
00069900
00070000
00070100
00070200
00070400
00070400
00070600
00070600
00071000
00071100
00071100
00071100
00071100
                                                  100
                                                  200
                                                  210
                                                  220
                                                                                                                ARRAY(LO)=IN-1000+JN-10+1
IF (MASS(LO).GT.MASS(L))GO TO 300
POSTN(LO)=POSTN(L)
SIGMA(LO)=SIGMA(L)
MASS(LO)=MASS(LO)+MASS(L)
MASS(L)=0.0
                                                  250
                                                  300
     00071700
                                                                                                                 CONTÍNÚE
                                                  500
                                                                                          CONTINUE
     00071800
                                                  900
```

```
RETURN
                                         END
                                        ***ZERO MASS OR LOW MASS PUFFS ARE SORTED OUT OF ARRAY
LOW MASS VALUE CURRENTLY SET TO 1.0 UNITS
SUBROUTINE PSORT(NPUFF, PMIN)
INTEGER*2 POSTN(05000), ARRAY(05000), SIGMA(05000)
REAL*4 MASS(05000)
COMMON/PUFFS/MASS, POSTN, ARRAY, SIGMA
IF(NPUFF.LT.2) RETURN
                                         LB≥
                                          LE≖]
                                 10 IF (MASS (LE) .GT.PMIN) GO TO 50
                                         LE=LE+]
                                         ĪĒ(ĒĒ.ĢŢ.NPUFF)GO TO 60
                                GO TO 10
50 MASS (LB) = MASS (LE)
POSTN (LB) = POSTN (LE)
ARRAY (LB) = ARRAY (LE)
SIGMA (LB) = SIGMA (LE)
                                         LB=LB+1
                                         LE=LE+]
 00074100
00074200
00074300
00074400
                                IF (LE.LE.NPUFF) GO TO 10 60 NPUFF=LB-1
RETURN
 00075900
00076100
00076200
00076300
00076400
00076500
00076600
00076800
00076800
00077100
00077100
00077300
                                                                     KGRDJ=KGRID*COSLAT(1)+0.5
                                                                     KGRDJ=KGRID*COSLAT(I)+0.5
IB=MAX0(I-KGRDI,1)
IE=MIN0(I+KGRDI,25)
JB=MAX0(J-KGRDJ,1)
JE=MIN0(J+KGRDJ,60)
JB1=MIN0(J+L,60)
JB1=MIN0(J+L,60)
JB1=MAX0(J-1,1)

DO 70 II=IB,IE

KSTA=KDSTN(II,JB)
IF(KSTA.LT.0)GO TO 90
KSTA=KDSTN(II,JE)
IF(KSTA.LT.0)GO TO 90
CONTINUE
IF(JB1,GE.J.OR.JE1,LE.J)GO
                                 70
 00077200
00077300
00077400
00077600
000777600
00077800
00078000
00078200
00078200
00078300
00078300
                                                                     IF (JB1.GE.J.OR.JE1.LE.J) GO TO 85
DO 75 JJ=JB1, JE1
KSTA=KDSTN(IB,JJ)
IF (KSTA.LT.0) GO TO 90
KSTA=KDSTN(IE,JJ)
IF (KSTA.LT.0) GO TO 90
CONTINUE
                                                                     CONTINUE
                                                       KB=KB+1
GO TO 100
                                                       KDSTN(I,J)=-KSTA
CONTINUE
                              90
100
 00078400
00078500
00078600
00078700
00078800
00078900
                                         IF (KB.EQ.0)GO TO 200
WRITE (6,150) KB
FORMAT (27X,14, UNAS
                                                                                     UNASSIGNED POSITIONS ON GRID')
                                         RETURN
                                         END
```